



FRSKY INSTALLATION GUIDE

- This ZIP file contains all the files necessary to configure the telemetry-capable devices, wirelessly from your transmitter.
- The Ethos system (minimum version 1.4) is required, as well as one of the F.Port or F.Bus protocols enabled at the receiver.
- Always use a sufficient cable diameter in case higher current throughput is needed.
- Unzip the archive to your hard drive, connect the transmitter using a USB cable, and enable Mass Storage operation (Ethos Suite). Copy the contents of the unzipped “scripts” folder to the “scripts” folder on the transmitter.
- You should be able to see the file structure similar to the picture on the right. Safely remove the transmitter from your PC and locate the Configuration menu. The installed configuration apps should be displayed on the second page:



- As soon as you enter any of the apps, the configuration values will be loaded from the connected telemetry sensor.
- Please note that, at the moment, the telemetry sensors contain fixed device and app IDs, so it is only possible to combine multiple sensors of different types. On the other hand, multiple instances of the same sensor type are not allowed.

RELEASE NOTES

Version Pack 1.1

- Added German language to all configuration apps.
- Added new compatible sensors: AMS and T125.
- Fixed several small issues regarding Ethos 1.6.

Version Pack 1.0

- Initial version